

Prepared (also subject responsible if other) ETH/RZD Péter Dimitrov +36 1 437 7244		No. 155 17-CNL 113 469 Uen		
Approved ETH/RZDC (Árpád Szakács)	Checked ETHCKY	Date 2006-08-21	Rev B	Reference GASK2

SCTPasp Test Port for TTCN-3 Toolset with TITAN, Function Specification

Contents

1	Introduction.....	2
1.1	Revision history	2
1.2	How to Read this Document.....	2
1.3	Scope	2
1.4	References	2
1.5	Abbreviations.....	3
1.6	Terminology	3
2	General.....	3
3	Function Specification	4
3.1	Implementation	4
3.1.1	Module structure.....	4
3.2	Configuration	5
3.3	Start Procedure	5
3.4	Connecting the SCTP ports.....	5
3.5	Sending/Receiving SCTP ASPs	5
3.6	Debugging	6
3.7	Error Handling	6
3.8	Closing Down	6
4	Limitations	6

Prepared (also subject responsible if other) ETH/RZD Péter Dimitrov +36 1 437 7244		No. 155 17-CNL 113 469 Uen		
Approved ETH/RZDC (Árpád Szakács)	Checked ETHCKY	Date 2006-08-21	Rev B	Reference GASK2

1 Introduction

1.1 Revision history

Date	Rev	Characteristics	Prepared
2005-09-14	PA1	First draft version	EPTEDIM
2006-01-20	A	Full revision	EPTEDIM
2006-01-24	PB1	Improved functionality added	EPTEDIM
2006-01-26	PB2	Corrected after review	EPTEDIM

1.2 How to Read this Document

This is the Function Specification for the SCTPasp test port. The SCTPasp test port is developed for the TTCN-3 Toolset with TITAN. This document is intended to be read together with Product Revision Information [4].

1.3 Scope

The purpose of this document is to specify the functionality of the SCTPasp test port. The document is primarily addressed to the end users of the product. Basic knowledge of TTCN-3 and TITAN TTCN-3 Test Executor is valuable when reading this document (see [1] and [3]).

This document is based on specifications of Stream Control Transmission Protocol (SCTP) defined by RFC 2960 [7] and on Socket API Extensions for Stream Control Transmission Protocol [6].

1.4 References

- [1] ETSI ES 201 873-1 v3.1.1 (2005-06)
The Testing and Test Control Notation version 3; Part 1: Core Language
- [2] 1/198 17-CRL 113 200 Uen
TITAN User Guide
- [3] 2/198 17-CRL 113 200 Uen
Programmer's Technical Reference for TITAN TTCN-3 Test Executor
- [4] 109 21-113 469 Uen
SCTPasp Test Port for TTCN-3 Toolset with TITAN, Product Revision Information
- [5] 198 17-113 469 Uen
SCTPasp Test Port for TTCN-3 Toolset with TITAN, User's Guide
- [6] draft-ietf-tsvwg-sctpsocket-10b.txt
Socket API Extensions for Stream Control Transmission Protocol (SCTP)
- [7] RFC 2960 (2000)
Stream Control Transmission Protocol

Prepared (also subject responsible if other) ETH/RZD Péter Dimitrov +36 1 437 7244		No. 155 17-CNL 113 469 Uen		
Approved ETH/RZDC (Árpád Szakács)	Checked ETHCKY	Date 2006-08-21	Rev B	Reference GASK2

1.5 Abbreviations

API	Application Program Interface
ASP	Abstract Service Primitive
RTE	Run-Time Environment
SCTP	Stream Control Transmission Protocol
SUT	System Under Test
TTCN-3	Testing and Test Control Notation version 3

1.6 Terminology

Sockets – The sockets is a method for communication between a client program and a server program in a network. A socket is defined as "the endpoint in a connection." Sockets are created and used with a set of programming requests or "function calls" sometimes called the sockets application-programming interface (API). The most common socket API is the Berkeley UNIX C language interface for sockets. Sockets can also be used for communication between processes within the same computer.

2 General

The SCTPasp Test Port makes it possible to execute test suites towards a SUT. The test port offers SCTP primitives to the test suite and communicates with the SUT.

The communication between the SCTPasp test port and the TITAN RTE is done by using the API functions described in [3]. The SCTPasp test port then transfers the SCTP messages to the SUT.

The figure 1 shows the overview of the system:




Figure 1.

Prepared (also subject responsible if other) ETH/RZD Péter Dimitrov +36 1 437 7244		No. 155 17-CNL 113 469 Uen		
Approved ETH/RZDC (Árpád Szakács)	Checked ETHCKY	Date 2006-08-21	Rev B	Reference GASK2

3 Function Specification

3.1 Implementation

The SCTP layer is implemented in the kernel of the operating system. The test port implements the communication between the SCTP socket and the TTCN-3 SCTP ASPs. The test port can work in two modes: simple mode and normal mode. The selection between these main modes is controlled by a test port parameter (`simple_mode`).

In simple mode the test port can work in two submodes: as a client (maintaining only one connection at a time) or as a server (maintaining several client connections at the same time). One-to-one style sockets are used in both client and server submodes. There is a special reconnect mode when the test port is used as a client. In reconnect mode the client automatically connect to an arbitrary server. If the connection fails a reconnection procedure will be initiated. This procedure will block the RTE, it is strongly recommended not to use the test port in reconnect mode.

In normal mode the test port can handle arbitrary number of servers and clients at the same time. Table 1. shows all available modes of the test port.

Simple mode		Normal mode
Client	Server	
<i>Reconnect</i>		

Table 1.

Note: while in simple mode the test port is backward compatible to the previous version of the SCTPasp test port, in normal mode there are several functional and semantic differences. For more information please refer to [5].

3.1.1 Module structure

The SCTPasp test port is implemented in the following TTCN-3 blocks:

- `SCTPasp_Types.ttcn`
- `SCTPasp_PortType.ttcn`

The file `SCTPasp_Types.ttcn` defines the SCTP ASPs. The port type is defined in `SCTPasp_PortType.ttcn`.

The C++ implementation of the test port is contained in the following files:

- `SCTPasp_PT.hh`
- `SCTPasp_PT.cc`

Prepared (also subject responsible if other) ETH/RZD Péter Dimitrov +36 1 437 7244		No. 155 17-CNL 113 469 Uen		
Approved ETH/RZDC (Árpád Szakács)	Checked ETHCKY	Date 2006-08-21	Rev B	Reference GASK2

3.2 Configuration

The configuration of the SCTPasp test port is done by the TITAN RTE configuration file. Beside the address and the port of the server and the operation mode several other SCTP layer options can be given as port parameters. When the operation mode is set to client, the port will operate as SCTP client socket, trying to connect to the given address and port. In case of server operation mode, the port will start an SCTP server on the given port and will be listening for new connections from client ports. In normal mode the test port can handle multiple client and server sockets at the same time.

Note: almost every parameter can be set by ASPs too. In normal mode this is the only way to configure several client and server sockets properly. For more information about configuring the test port please refer to [5].

3.3 Start Procedure

After the configuration is done, the user has to make sure that the target system is up and running. When the executable test suite is started it initializes the SCTP socket. After the start procedure the SCTP server type port is already listening for server connections. In the case of using test ports in client mode the connection to the server can be automatic too when they are in reconnect mode. In normal mode all type of connections shall be initiated manually by sending out the proper ASPs.

3.4 Connecting the SCTP ports

In simple mode the SCTP connection is initiated by the client type port, and is set up by sending an ASP_SCTP_Connect abstract service primitive. After the connection has been set up, transmission of the ASPs can begin. The ASP_SCTP_Connect primitive is restricted to be used only in client mode. Using it in server mode will result a TTCN error. As it was mentioned above there is another way to connect to an arbitrary server port, setting reconnect mode. In normal mode arbitrary number of ASP_SCTP_Connect, ASP_SCTP_ConnectFrom can be sent. Beside the clients arbitrary number of servers can be started too by sending ASP_SCTP_Listen.

3.5 Sending/Receiving SCTP ASPs

When the communication between the SCTP test port and the target system is set up, the test port starts translating the SCTP primitives to SCTP packets (and vice versa) between the TITAN RTE and the SUT. For more information about available ASPs and there usage please refer to [5].

Prepared (also subject responsible if other) ETH/RZD Péter Dimitrov +36 1 437 7244		No. 155 17-CNL 113 469 Uen		
Approved ETH/RZDC (Árpád Szakács)	Checked ETHCKY	Date 2006-08-21	Rev B	Reference GASK2

3.6 Debugging

The type of information that will be logged can be categorized into two groups. The first one consists of information that shows the flow of the internal execution of the test port, e.g. important events, which function that is currently executing etc. The second group deals with presenting valuable data, e.g. presenting the content of a PDU. The logging printouts will be directed to the RTE log file. The user is able to decide whether logging is to take place or not by setting appropriate configuration data.

3.7 Error Handling

Erroneous behaviour detected during runtime is shown on the console and directed into the RTE log file. The following two types of messages are taken care of:

- Errors: information about errors detected is provided. If an error occurs the execution will stop immediately.
- Warnings: information about warnings detected is provided. The execution continues after the warning is shown.

3.8 Closing Down

After the test port has executed all test cases it will stop automatically. It will close down the SCTP socket towards the SUT and terminate.

The execution of the test suite can be stopped at any time by pressing <Ctrl>-c. Even when execution is interrupted with <Ctrl>-c the socket is still closed.

4 Limitations

Supported platforms: Solaris 10, SUSE Linux 9.1 and above.

Multihoming is not supported. If you use the SCTPasp Test Port on a machine with multiple interfaces then by default an arbitrary IP address will be chosen for the SCTP socket. So in this case it is recommended to specify the bind address in the TITAN RTE configuration file. In normal mode both the client and server type ports can choose a bind address by ASP_SCTP_ConnectFrom and ASP_SCTP_Listen.

IPv6 is not supported.